

Context for WWAT Design

- Assist Michigan in implementation of the Great Lakes-St. Lawrence River Basin Compact and Agreement
- Specifically—define and prohibit Adverse Resource Impacts (ARI) to water-dependent natural resources in streams
- Process designed to ensure proposed withdrawals are legal—with burden on proposer



Process vs Tool

- The WWAT is part of the Water Withdrawal Assessment Process
- Process includes all sources of water: Great Lakes, inland lakes, stream, groundwater
- Less than 100,000 GPD—not regulated
- Greater than 2,000,000 GPD—permit needed
- In between, registration, no permit, WWAT can be used for withdrawals that may affect streamflow
- Peer Review of Process



WWAT

- WWAT is a screen to relieve the State of the need to evaluate all proposed withdrawals
- WWAT will indicate whether or not a proposed withdrawal may cause an ARI
- WWAT is available on-line
- Proposed withdrawals that do not pass thru screen must receive site-specific review and meet same criteria in WWAT
- Burden is on user to not cause ARI



WWAT—Three Models


- Flow—How much water is in the stream?
- Withdrawal—How much will a proposed withdrawal reduce streamflow?
- Fish—How will reduced streamflow affect fish?

SAVE THE FLOW—The fishes are indicators of ecologically appropriate flows




Flow Model

- Chose low summer flow as Index Flow
- WWAT uses half the Index Flow—safety
- Based on regression from USGS gages



Water Use in Ohio






Withdrawal Model

- From stream—100 percent removed from index flow
- From groundwater—May be less than 100 percent



Groundwater-Surface Water Interaction






Withdrawal Model—Groundwater

- From groundwater—effect on stream depends on aquifer type, depth of well, distance from well, and pumping pattern
- Aquifer type based on GWIM
- Deeper wells affect more streams, but the effect is less on each
- Same for wells near watershed boundaries
- Intermittent well pumping may have less affect on stream than continuous pumping




Fish Model

 Response Curves predict how characteristic fishes will respond to changes in index flow



Fish Surveys

1389 sites with fish assemblage data







Stream Classification—Response Curves


Proportion of initial fish population metric


Cold







Cold Trans.










Cool









Warm



0.8 0.6 0.4 0.2





Streams


Sm. Rivers

Lg. Rivers




Proportion of index flow removed


Response Curves—Gradient of Risk





ARI Defined by Legislature





NHDPlus


34,000 stream reaches in Michigan

Grouped into ~5300 valley segments

Each attributed with:

- index flow
- aquifer type
- response curve based on stream type







_ | X


0 -


WATER WITHDRAWAL ASSESSMENT TOOL

GIS Tools	
Zoom In	Zoom Out
Address	Move Map
Back	Erase
Identify	Toggle Legend
Measure	Set Scale
Overview Map	Print
Query Builder	Help
New Withdrawal	









Done

Internet

Development of WWAT

- Compact and Michigan Legislation provided the need to define adverse resource impact
- Science provided the context within which to define "adverse"
- State government made policy definition of "adverse"
- Water Resource Conservation Advisory Council provided a collaborative context for policy makers and scientists to iteratively inform each other




Application of WWAT

- Screens "in" proposed withdrawals that will not cause ARIs
- Provides information that can be used for site-specific review
- Provides context for cumulative impacts, since each valley segment has a defined amount of water available in perpetuity



Great Lakes Restoration Initiative



- Flow
- Withdrawal
- Fish
- Require State input for stream classification
- Flexible to accept State options
- Framework for application of ELOHA



Acknowledgements

- Paul Seelbach, USGS (formerly MDNR)
- Dave Hamilton, MDNRE
- Howard Reeves, USGS
- Jeremiah Asher, MSU-IWR
- Michigan Legislature
- WRCAC
- http://www.miwwat.org/
- Includes links to publications



Predevelopment Regional Water Budget

Direct Precipitation Direct Evaporation Direct Precipitation Direct Evaporation to Lakes from Lakes to Lakes from Lakes 229 x 103 ft3/sec 178 x 103 ft3/sec 229 x 103 ft3/sec 178 x 103 ft3/sec Direct Run off Direct Run off and stream flow and stream flow Flow out St. Lawrence River 220 x 103 ft3/sec **Great Lakes Storage** Flow out St. Lawrence River 220 x 103 ft3/sec 271 x 103 ft3/sec Great Lakes Storage 271 x 103 ft3/sec 7.9 x 1014 ft3 7.9 x 1014 ft3 Withdrawal (all Surface Water) 63 x 103 ft3/sec Direct Ground-Water Precipitation to Land Area of Basin Direct Return Discharge Ground-Water Flow 505 x 103 ft3/sec 5 x 10³ Discharge 62 x 103 ft3/sec Consumptive ft3/sec Evapotranspiration from 5 x 103 Use Land Area of Basin Precipitation ft3/sec 3 x 103 ft3/sec 284 x 103 ft3/sec and evapotranspiration Ground Withdrawal Water 2 x 103 ft3/sec Baseflow to Streams Storage¹ Ground' (≈ aguifer recharge) Water 151 x 103 ft3/sec Flow in from Flow out to 1.4 x 1014 ft3 Baseflow to Streams adjacent basins adjacent basins Storage¹ (≈ aquifer recharge) 1U.S. part of the Great Lakes Basin 151 x 103 ft3/sec 1.4 x 1014 ft3

Developed Regional Water Budget

